

RF24 Class Reference

```
#include <RF24.h>
```

Public Member Functions

Primary public interface

These are the main methods you need to operate the chip

RF24 (uint8_t _cepin, uint8_t _cspin)

RF24 (uint8_t _cepin, uint8_t _cspin, uint32_t spispeed)

bool **begin** (void)

void **startListening** (void)

void **stopListening** (void)

bool **available** (void)

void **read** (void *buf, uint8_t len)

bool **write** (const void *buf, uint8_t len)

void **openWritingPipe** (const uint8_t *address)

void **openReadingPipe** (uint8_t number, const uint8_t *address)

Deprecated

Methods provided for backwards compability.

void **openReadingPipe** (uint8_t number, uint64_t address)

void **openWritingPipe** (uint64_t address)

Protected Member Functions

void **beginTransaction** ()

void **endTransaction** ()

Advanced Operation

Methods you can use to drive the chip in more advanced ways

bool **failureDetected**

void **printDetails** (void)

bool **available** (uint8_t *pipe_num)

bool **rxFifoFull** ()

void **powerDown** (void)

void	powerUp	(void)
bool	write	(const void *buf, uint8_t len, const bool multicast)
bool	writeFast	(const void *buf, uint8_t len)
bool	writeFast	(const void *buf, uint8_t len, const bool multicast)
bool	writeBlocking	(const void *buf, uint8_t len, uint32_t timeout)
bool	txStandBy	()
bool	txStandBy	(uint32_t timeout, bool startTx=0)
void	writeAckPayload	(uint8_t pipe, const void *buf, uint8_t len)
bool	isAckPayloadAvailable	(void)
void	whatHappened	(bool &tx_ok, bool &tx_fail, bool &rx_ready)
void	startFastWrite	(const void *buf, uint8_t len, const bool multicast, bool startTx=1)
void	startWrite	(const void *buf, uint8_t len, const bool multicast)
void	reUseTX	()
uint8_t	flush_tx	(void)
bool	testCarrier	(void)
bool	testRPD	(void)
bool	isValid	()
void	closeReadingPipe	(uint8_t pipe)

Optional Configurators

Methods you can use to get or set the configuration of the chip. None are required. Calling **begin()** sets up a reasonable set of defaults.

uint32_t	txDelay
uint32_t	csDelay =5
void	setAddressWidth (uint8_t a_width)
void	setRetries (uint8_t delay , uint8_t count)
void	setChannel (uint8_t channel)
uint8_t	getChannel (void)
void	setPayloadSize (uint8_t size)
uint8_t	getPayloadSize (void)
uint8_t	getDynamicPayloadSize (void)
void	enableAckPayload (void)
void	enableDynamicPayloads (void)
void	enableDynamicAck ()
bool	isPVariant (void)
void	setAutoAck (bool enable)
void	setAutoAck (uint8_t pipe, bool enable)

void	setPALevel	(uint8_t level)
uint8_t	getPALevel	(void)
bool	setDataRate	(rf24_datarate_e speed)
rf24_datarate_e	getDataRate	(void)
void	setCRCLength	(rf24_crclength_e length)
rf24_crclength_e	getCRCLength	(void)
void	disableCRC	(void)
void	maskIRQ	(bool tx_ok, bool tx_fail, bool rx_ready)

Detailed Description

Driver for nRF24L01(+) 2.4GHz Wireless Transceiver

Examples:
[gettingstarted.cpp](#), [GettingStarted.ino](#), [gettingstarted_call_response.cpp](#),
[GettingStarted_CallResponse.ino](#), [GettingStarted_HandlingData.ino](#), [pingpair_ack.ino](#),
[pingpair_dyn.cpp](#), [pingpair_dyn.ino](#), [pingpair_irq.ino](#), [pingpair_irq_simple.ino](#), [pingpair_sleepy.ino](#),
[rf24ping85.ino](#), [scanner.ino](#), [starping.pde](#), [transfer.cpp](#), [Transfer.ino](#), and [TransferTimeouts.ino](#).

Definition at line **51** of file **RF24.h**.

Constructor & Destructor Documentation

RF24::RF24 (uint8_t **_cepin**,
uint8_t **_cspin**
)

Arduino Constructor

Creates a new instance of this driver. Before using, you create an instance and send in the unique pins that this chip is connected to.

Parameters

`_cepin` The pin attached to Chip Enable on the RF module

`_cspin` The pin attached to Chip Select

Definition at line **418** of file **RF24.cpp**.

```
RF24::RF24 ( uint8_t  _cepin,  
             uint8_t  _cspin,  
             uint32_t spispeed  
            )
```

Optional Linux Constructor

Creates a new instance of this driver. Before using, you create an instance and send in the unique pins that this chip is connected to.

Parameters

- _cepin** The pin attached to Chip Enable on the RF module
- _cspin** The pin attached to Chip Select
- spispeed** For RPi, the SPI speed in MHZ ie: BCM2835_SPI_SPEED_8MHZ

Member Function Documentation

```
void RF24::beginTransaction ( )
```

inline protected

SPI transactions

Common code for SPI transactions including CSN toggle

Definition at line **68** of file **RF24.cpp**.

```
void RF24::endTransaction ( )
```

inline protected

Definition at line **77** of file **RF24.cpp**.

```
bool RF24::begin ( void )
```

Begin operation of the chip

Call this in setup(), before calling any other methods.

```
radio.begin()
```

Definition at line **571** of file **RF24.cpp**.

void RF24::startListening (void)

Start listening on the pipes opened for reading.

1. Be sure to call **openReadingPipe()** first.
2. Do not call **write()** while in this mode, without first calling **stopListening()**.
3. Call **available()** to check for incoming traffic, and **read()** to get it.

```
Open reading pipe 1 using address CCCECCCECC  
byte address[] = { 0xCC,0xCE,0xCC,0xCE,0xCC };  
radio.openReadingPipe(1,address);  
radio.startListening();
```

Definition at line **696** of file **RF24.cpp**.

void RF24::stopListening (void)

Stop listening for incoming messages, and switch to transmit mode.

Do this before calling **write()**.

```
radio.stopListening();  
radio.write(&data,sizeof(data));
```

Definition at line **727** of file **RF24.cpp**.

bool RF24::available (void)

Check whether there are bytes available to be read

```
if(radio.available()){  
    radio.read(&data,sizeof(data));  
}
```

Returns

True if there is a payload available, false if none is

Definition at line **1060** of file **RF24.cpp**.

```
void RF24::read ( void *   buf,  
                  uint8_t len  
                  )
```

Read the available payload

The size of data read is the fixed payload size, see [getPayloadSize\(\)](#)

Note

I specifically chose 'void*' as a data type to make it easier for beginners to use. No casting needed.

No longer boolean. Use `available` to determine if packets are available. Interrupt flags are now cleared during reads instead of when calling [available\(\)](#).

Parameters

buf Pointer to a buffer where the data should be written

len Maximum number of bytes to read into the buffer

```
if (radio.available()) {  
    radio.read(&data, sizeof(data));  
}
```

Returns

No return value. Use [available\(\)](#).

Definition at line **1087** of file **RF24.cpp**.

```
bool RF24::write ( const void * buf,
                  uint8_t len
                  )
```

Be sure to call **openWritingPipe()** first to set the destination of where to write to.

This blocks until the message is successfully acknowledged by the receiver or the timeout/retransmit maxima are reached. In the current configuration, the max delay here is 60-70ms.

The maximum size of data written is the fixed payload size, see **getPayloadSize()**. However, you can write less, and the remainder will just be filled with zeroes.

TX/RX/RT interrupt flags will be cleared every time write is called

Parameters

buf Pointer to the data to be sent

len Number of bytes to be sent

```
radio.stopListening();
radio.write(&data, sizeof(data));
```

Returns

True if the payload was delivered successfully false if not

Definition at line **831** of file **RF24.cpp**.

```
void RF24::openWritingPipe ( const uint8_t * address )
```

New: Open a pipe for writing via byte array. Old addressing format retained for compatibility.

Only one writing pipe can be open at once, but you can change the address you'll write to. Call **stopListening()** first.

Addresses are assigned via a byte array, default is 5 byte address length s *

```
uint8_t addresses[][6] = {"1Node", "2Node"};
radio.openWritingPipe(addresses[0]);
```

```
uint8_t address[] = { 0xCC, 0xCE, 0xCC, 0xCE, 0xCC };
radio.openWritingPipe(address);
address[0] = 0x33;
radio.openReadingPipe(1, address);
```

See also

setAddressWidth

Parameters

address The address of the pipe to open. Coordinate these pipe addresses amongst nodes on the network.

Definition at line **1128** of file **RF24.cpp**.

```
void RF24::openReadingPipe ( uint8_t      number,  
                             const uint8_t * address  
                             )
```

Open a pipe for reading

Up to 6 pipes can be open for reading at once. Open all the required reading pipes, and then call [startListening\(\)](#).

See also

[openWritingPipe](#)

[setAddressWidth](#)

Note

Pipes 0 and 1 will store a full 5-byte address. Pipes 2-5 will technically only store a single byte, borrowing up to 4 additional bytes from pipe #1 per the assigned address width.

Warning

Pipes 1-5 should share the same address, except the first byte. Only the first byte in the array should be unique, e.g.

```
uint8_t addresses[][6] = {"1Node", "2Node"};  
openReadingPipe(1, addresses[0]);  
openReadingPipe(2, addresses[1]);
```

Pipe 0 is also used by the writing pipe. So if you open pipe 0 for reading, and then [startListening\(\)](#), it will overwrite the writing pipe. Ergo, do an [openWritingPipe\(\)](#) again before [write\(\)](#).

Parameters

number Which pipe# to open, 0-5.

address The 24, 32 or 40 bit address of the pipe to open.

Definition at line [1190](#) of file [RF24.cpp](#).

```
void RF24::printDetails ( void )
```

Print a giant block of debugging information to stdout

Warning

Does nothing if stdout is not defined. See fdevopen in stdio.h The [printf.h](#) file is included with the library for Arduino.

```
#include <printf.h>  
setup(){  
  Serial.begin(115200);  
  printf_begin();  
  ...  
}
```

Definition at line [512](#) of file [RF24.cpp](#).

bool RF24::available (uint8_t * pipe_num)

Test whether there are bytes available to be read in the FIFO buffers.

Parameters

[out] **pipe_num** Which pipe has the payload available

```
uint8_t pipeNum;
if(radio.available(&pipeNum)){
    radio.read(&data,sizeof(data));
    Serial.print("Got data on pipe");
    Serial.println(pipeNum);
}
```

Returns

True if there is a payload available, false if none is

Definition at line **1067** of file **RF24.cpp**.

bool RF24::rxFifoFull ()

Check if the radio needs to be read. Can be used to prevent data loss

Returns

True if all three 32-byte radio buffers are full

Definition at line **956** of file **RF24.cpp**.

void RF24::powerDown (void)

Enter low-power mode

To return to normal power mode, call **powerUp()**.

Note

After calling **startListening()**, a basic radio will consume about 13.5mA at max PA level. During active transmission, the radio will consume about 11.5mA, but this will be reduced to 26uA (.026mA) between sending. In full powerDown mode, the radio will consume approximately 900nA (.0009mA)

```
radio.powerDown();
avr_enter_sleep_mode(); // Custom function to sleep the device
radio.powerUp();
```

Definition at line **755** of file **RF24.cpp**.

void RF24::powerUp (void)

Leave low-power mode - required for normal radio operation after calling **powerDown()**

To return to low power mode, call **powerDown()**.

Note

This will take up to 5ms for maximum compatibility

Definition at line **764** of file **RF24.cpp**.

```
bool RF24::write ( const void * buf,  
                  uint8_t len,  
                  const bool multicast  
                  )
```

Write for single NOACK writes. Optionally disables acknowledgements/autoretries for a single write.

Note

enableDynamicAck() must be called to enable this feature

Can be used with **enableAckPayload()** to request a response

See also

enableDynamicAck()

setAutoAck()

write()

Parameters

buf Pointer to the data to be sent

len Number of bytes to be sent

multicast Request ACK (0), NOACK (1)

Definition at line **795** of file **RF24.cpp**.

```
bool RF24::writeFast ( const void * buf,
                      uint8_t len
                      )
```

This will not block until the 3 FIFO buffers are filled with data. Once the FIFOs are full, writeFast will simply wait for success or timeout, and return 1 or 0 respectively. From a user perspective, just keep trying to send the same data. The library will keep auto retrying the current payload using the built in functionality.

Warning

It is important to never keep the nRF24L01 in TX mode and FIFO full for more than 4ms at a time. If the auto retransmit is enabled, the nRF24L01 is never in TX mode long enough to disobey this rule. Allow the FIFO to clear by issuing `txStandBy()` or ensure appropriate time between transmissions.

Example (Partial blocking):

```
radio.writeFast(&buf,32); // Writes 1 payload to the buffers
txStandBy();             // Returns 0 if failed. 1 if success. Blocks only until
MAX_RT timeout or success. Data flushed on fail.

radio.writeFast(&buf,32); // Writes 1 payload to the buffers
txStandBy(1000);         // Using extended timeouts, returns 1 if success. Retries
failed payloads for 1 seconds before returning 0.
```

See also

`txStandBy()`

`write()`

`writeBlocking()`

Parameters

buf Pointer to the data to be sent

len Number of bytes to be sent

Returns

True if the payload was delivered successfully false if not

Definition at line **914** of file **RF24.cpp**.

```
bool RF24::writeFast ( const void * buf,  
                      uint8_t      len,  
                      const bool    multicast  
                      )
```

WriteFast for single NOACK writes. Disables acknowledgements/autoretries for a single write.

Note

[enableDynamicAck\(\)](#) must be called to enable this feature

See also

[enableDynamicAck\(\)](#)

[setAutoAck\(\)](#)

Parameters

buf Pointer to the data to be sent

len Number of bytes to be sent

multicast Request ACK (0) or NOACK (1)

Definition at line [880](#) of file [RF24.cpp](#).

```

bool RF24::writeBlocking ( const void * buf,
                          uint8_t len,
                          uint32_t timeout
                          )

```

This function extends the auto-retry mechanism to any specified duration. It will not block until the 3 FIFO buffers are filled with data. If so the library will auto retry until a new payload is written or the user specified timeout period is reached.

Warning

It is important to never keep the nRF24L01 in TX mode and FIFO full for more than 4ms at a time. If the auto retransmit is enabled, the nRF24L01 is never in TX mode long enough to disobey this rule. Allow the FIFO to clear by issuing `txStandBy()` or ensure appropriate time between transmissions.

Example (Full blocking):

```

radio.writeBlocking(&buf,32,1000); //Wait up to 1 second to write 1 payload to the
buffers
txStandBy(1000);                  //Wait up to 1 second for the payload to send. Return
1 if ok, 0 if failed.              //Blocks only until user timeout or success. Data
flushed on fail.

```

Note

If used from within an interrupt, the interrupt should be disabled until completion, and `sei()`; called to enable `millis()`.

See also

`txStandBy()`

`write()`

`writeFast()`

Parameters

- buf** Pointer to the data to be sent
- len** Number of bytes to be sent
- timeout** User defined timeout in milliseconds.

Returns

True if the payload was loaded into the buffer successfully false if not

Definition at line **837** of file **RF24.cpp**.

bool RF24::txStandBy ()

This function should be called as soon as transmission is finished to drop the radio back to STANDBY-I mode. If not issued, the radio will remain in STANDBY-II mode which, per the data sheet, is not a recommended operating mode.

Note

When transmitting data in rapid succession, it is still recommended by the manufacturer to drop the radio out of TX or STANDBY-II mode if there is time enough between sends for the FIFOs to empty. This is not required if auto-ack is enabled.

Relies on built-in auto retry functionality.

Example (Partial blocking):

```
radio.writeFast(&buf,32);  
radio.writeFast(&buf,32);  
radio.writeFast(&buf,32);  
bool ok = txStandBy();  
on fail.
```

//Fills the FIFO buffers up
//Returns 0 if failed. 1 if success.
//Blocks only until MAX_RT timeout or success. Data flushed

See also

txStandBy(unsigned long timeout)

Returns

True if transmission is successful

Definition at line **961** of file **RF24.cpp**.

```

bool RF24::txStandBy ( uint32_t timeout,
                      bool      startTx = 0
                    )

```

This function allows extended blocking and auto-retries per a user defined timeout

Fully Blocking Example:

```

radio.writeFast(&buf,32);
radio.writeFast(&buf,32);
radio.writeFast(&buf,32); //Fills the FIFO buffers up
bool ok = txStandBy(1000); //Returns 0 if failed after 1 second of retries. 1 if success.
                          //Blocks only until user defined timeout or success. Data
                          flushed on fail.

```

Note

If used from within an interrupt, the interrupt should be disabled until completion, and sei(); called to enable millis().

Parameters

timeout Number of milliseconds to retry failed payloads

Returns

True if transmission is successful

Definition at line **989** of file **RF24.cpp**.

```
void RF24::writeAckPayload ( uint8_t      pipe,
                             const void * buf,
                             uint8_t      len
                           )
```

Write an ack payload for the specified pipe

The next time a message is received on pipe, the data in buf will be sent back in the acknowledgement.

See also

[enableAckPayload\(\)](#)

[enableDynamicPayloads\(\)](#)

Warning

Only three of these can be pending at any time as there are only 3 FIFO buffers.

Dynamic payloads must be enabled.

Note

Ack payloads are handled automatically by the radio chip when a payload is received. Users should generally write an ack payload as soon as [startListening\(\)](#) is called, so one is available when a regular payload is received.

Ack payloads are dynamic payloads. This only works on pipes 0&1 by default. Call [enableDynamicPayloads\(\)](#) to enable on all pipes.

Parameters

pipe Which pipe# (typically 1-5) will get this response.

buf Pointer to data that is sent

len Length of the data to send, up to 32 bytes max. Not affected by the static payload set by [setPayloadSize\(\)](#).

Definition at line **1291** of file **RF24.cpp**.

```
bool RF24::isAckPayloadAvailable ( void )
```

Determine if an ack payload was received in the most recent call to [write\(\)](#). The regular [available\(\)](#) can also be used.

Call [read\(\)](#) to retrieve the ack payload.

Returns

True if an ack payload is available.

Definition at line **1322** of file **RF24.cpp**.


```
void RF24::whatHappened ( bool & tx_ok,  
                        bool & tx_fail,  
                        bool & rx_ready  
                        )
```

Call this when you get an interrupt to find out why

Tells you what caused the interrupt, and clears the state of interrupts.

Parameters

- [out] **tx_ok** The send was successful (TX_DS)
- [out] **tx_fail** The send failed, too many retries (MAX_RT)
- [out] **rx_ready** There is a message waiting to be read (RX_DS)

Definition at line **1099** of file **RF24.cpp**.

```
void RF24::startFastWrite ( const void * buf,  
                           uint8_t      len,  
                           const bool    multicast,  
                           bool          startTx = 1  
                           )
```

Non-blocking write to the open writing pipe used for buffered writes

Note

Optimization: This function now leaves the CE pin high, so the radio will remain in TX or STANDBY-II Mode until a **txStandBy()** command is issued. Can be used as an alternative to **startWrite()** if writing multiple payloads at once.

Warning

It is important to never keep the nRF24L01 in TX mode with FIFO full for more than 4ms at a time. If the auto retransmit/autoAck is enabled, the nRF24L01 is never in TX mode long enough to disobey this rule. Allow the FIFO to clear by issuing **txStandBy()** or ensure appropriate time between transmissions.

See also

write()

writeFast()

startWrite()

writeBlocking()

For single noAck writes see:

See also

enableDynamicAck()

setAutoAck()

Parameters

buf Pointer to the data to be sent

len Number of bytes to be sent

multicast Request ACK (0) or NOACK (1)

Returns

True if the payload was delivered successfully false if not

Definition at line **925** of file **RF24.cpp**.

```
void RF24::startWrite ( const void * buf,  
                        uint8_t len,  
                        const bool multicast  
                        )
```

Non-blocking write to the open writing pipe

Just like [write\(\)](#), but it returns immediately. To find out what happened to the send, catch the IRQ and then call [whatHappened\(\)](#).

See also

[write\(\)](#)

[writeFast\(\)](#)

[startFastWrite\(\)](#)

[whatHappened\(\)](#)

For single noAck writes see:

See also

[enableDynamicAck\(\)](#)

[setAutoAck\(\)](#)

Parameters

buf Pointer to the data to be sent

len Number of bytes to be sent

multicast Request ACK (0) or NOACK (1)

Definition at line [939](#) of file [RF24.cpp](#).

void RF24::reUseTX ()

This function is mainly used internally to take advantage of the auto payload re-use functionality of the chip, but can be beneficial to users as well.

The function will instruct the radio to re-use the data in the FIFO buffers, and instructs the radio to re-send once the timeout limit has been reached. Used by writeFast and writeBlocking to initiate retries when a TX failure occurs. Retries are automatically initiated except with the standard **write()**. This way, data is not flushed from the buffer until switching between modes.

Note

This is to be used AFTER auto-retry fails if wanting to resend using the built-in payload reuse features. After issuing **reUseTX()**, it will keep reending the same payload forever or until a payload is written to the FIFO, or a flush_tx command is given.

Definition at line **871** of file **RF24.cpp**.

uint8_t RF24::flush_tx (void)

Empty the transmit buffer. This is generally not required in standard operation. May be required in specific cases after **stopListening()** , if operating at 250KBPS data rate.

Returns

Current value of status register

Definition at line **326** of file **RF24.cpp**.

bool RF24::testCarrier (void)

Test whether there was a carrier on the line for the previous listening period.

Useful to check for interference on the current channel.

Returns

true if was carrier, false if not

Definition at line **1365** of file **RF24.cpp**.

bool RF24::testRPD (void)

Test whether a signal (carrier or otherwise) greater than or equal to -64dBm is present on the channel. Valid only on nRF24L01P (+) hardware. On nRF24L01, use **testCarrier()**.

Useful to check for interference on the current channel and channel hopping strategies.

```
bool goodSignal = radio.testRPD();
if(radio.available()){
  Serial.println(goodSignal ? "Strong signal > 64dBm" : "Weak signal < 64dBm" );
  radio.read(0,0);
}
```

Returns

true if signal => -64dBm, false if not

Definition at line **1372** of file **RF24.cpp**.

bool RF24::isValid ()

inline

Test whether this is a real radio, or a mock shim for debugging. Setting either pin to 0xff is the way to indicate that this is not a real radio.

Returns

true if this is a legitimate radio

Definition at line **643** of file **RF24.h**.

void RF24::closeReadingPipe (uint8_t pipe)

Close a pipe after it has been previously opened. Can be safely called without having previously opened a pipe.

Parameters

pipe Which pipe # to close, 0-5.

Definition at line **1218** of file **RF24.cpp**.

void RF24::setAddressWidth (uint8_t a_width)

Set the address width from 3 to 5 bytes (24, 32 or 40 bit)

Parameters

a_width The address width to use: 3,4 or 5

Definition at line **1179** of file **RF24.cpp**.

```
void RF24::setRetries ( uint8_t delay,
                        uint8_t count
                      )
```

Set the number and delay of retries upon failed submit

Parameters

delay How long to wait between each retry, in multiples of 250us, max is 15. 0 means 250us, 15 means 4000us.

count How many retries before giving up, max 15

Definition at line **1531** of file **RF24.cpp**.

```
void RF24::setChannel ( uint8_t channel )
```

Set RF communication channel

Parameters

channel Which RF channel to communicate on, 0-125

Definition at line **437** of file **RF24.cpp**.

```
uint8_t RF24::getChannel ( void )
```

Get RF communication channel

Returns

The currently configured RF Channel

Definition at line **443** of file **RF24.cpp**.

```
void RF24::setPayloadSize ( uint8_t size )
```

Set Static Payload Size

This implementation uses a pre-established fixed payload size for all transmissions. If this method is never called, the driver will always transmit the maximum payload size (32 bytes), no matter how much was sent to **write()**.

Parameters

size The number of bytes in the payload

Definition at line **450** of file **RF24.cpp**.

uint8_t RF24::getPayloadSize (void)

Get Static Payload Size

See also

[setPayloadSize\(\)](#)

Returns

The number of bytes in the payload

Definition at line [457](#) of file [RF24.cpp](#).

uint8_t RF24::getDynamicPayloadSize (void)

Get Dynamic Payload Size

For dynamic payloads, this pulls the size of the payload off the chip

Note

Corrupt packets are now detected and flushed per the manufacturer.

```
if(radio.available()){
    if(radio.getDynamicPayloadSize() < 1){
        // Corrupt payload has been flushed
        return;
    }
    radio.read(&data,sizeof(data));
}
```

Returns

Payload length of last-received dynamic payload

Definition at line [1036](#) of file [RF24.cpp](#).

void RF24::enableAckPayload (void)

Enable custom payloads on the acknowledge packets

Ack payloads are a handy way to return data back to senders without manually changing the radio modes on both units.

Note

Ack payloads are dynamic payloads. This only works on pipes 0&1 by default. Call [enableDynamicPayloads\(\)](#) to enable on all pipes.

Definition at line [1256](#) of file [RF24.cpp](#).

void RF24::enableDynamicPayloads (void)

Enable dynamically-sized payloads

This way you don't always have to send large packets just to send them once in a while. This enables dynamic payloads on ALL pipes.

Definition at line **1235** of file **RF24.cpp**.

void RF24::enableDynamicAck (void)

Enable dynamic ACKs (single write multicast or unicast) for chosen messages

Note

To enable full multicast or per-pipe multicast, use **setAutoAck()**

Warning

This MUST be called prior to attempting single write NOACK calls

```
radio.enableDynamicAck();  
radio.write(&data,32,1); // Sends a payload with no acknowledgement requested  
radio.write(&data,32,0); // Sends a payload using auto-retry/autoACK
```

Definition at line **1277** of file **RF24.cpp**.

bool RF24::isPVariant (void)

Determine whether the hardware is an nRF24L01+ or not.

Returns

true if the hardware is nRF24L01+ (or compatible) and false if its not.

Definition at line **1329** of file **RF24.cpp**.

void RF24::setAutoAck (bool enable)

Enable or disable auto-acknowledge packets

This is enabled by default, so it's only needed if you want to turn it off for some reason.

Parameters

enable Whether to enable (true) or disable (false) auto-acks

Definition at line **1336** of file **RF24.cpp**.


```
void RF24::setAutoAck ( uint8_t pipe,
                        bool enable
                      )
```

Enable or disable auto-acknowledge packets on a per pipeline basis.

AA is enabled by default, so it's only needed if you want to turn it off/on for some reason on a per pipeline basis.

Parameters

pipe Which pipeline to modify

enable Whether to enable (true) or disable (false) auto-acks

Definition at line **1346** of file **RF24.cpp**.

```
void RF24::setPALevel ( uint8_t level )
```

Set Power Amplifier (PA) level to one of four levels: RF24_PA_MIN, RF24_PA_LOW, RF24_PA_HIGH and RF24_PA_MAX

The power levels correspond to the following output levels respectively: NRF24L01: -18dBm, -12dBm, -6dBm, and 0dBm

SI24R1: -6dBm, 0dBm, 3dBm, and 7dBm.

Parameters

level Desired PA level.

Definition at line **1379** of file **RF24.cpp**.

```
uint8_t RF24::getPALevel ( void )
```

Fetches the current PA level.

NRF24L01: -18dBm, -12dBm, -6dBm and 0dBm SI24R1: -6dBm, 0dBm, 3dBm, 7dBm

Returns

Returns values 0 to 3 representing the PA Level.

Definition at line **1396** of file **RF24.cpp**.

bool RF24::setDataRate (rf24_datarate_e speed)

Set the transmission data rate

Warning

setting RF24_250KBPS will fail for non-plus units

Parameters

speed RF24_250KBPS for 250kbs, RF24_1MBPS for 1Mbps, or RF24_2MBPS for 2Mbps

Returns

true if the change was successful

Definition at line **1404** of file **RF24.cpp**.

rf24_datarate_e RF24::getDataRate (void)

Fetches the transmission data rate

Returns

Returns the hardware's currently configured datarate. The value is one of 250kbs, RF24_1MBPS for 1Mbps, or RF24_2MBPS, as defined in the rf24_datarate_e enum.

Definition at line **1454** of file **RF24.cpp**.

void RF24::setCRCLength (rf24_crclength_e length)

Set the CRC length

CRC checking cannot be disabled if auto-ack is enabled

Parameters

length RF24_CRC_8 for 8-bit or RF24_CRC_16 for 16-bit

Definition at line **1481** of file **RF24.cpp**.

rf24_crclength_e RF24::getCRCLength (void)

Get the CRC length

CRC checking cannot be disabled if auto-ack is enabled

Returns

RF24_CRC_DISABLED if disabled or RF24_CRC_8 for 8-bit or RF24_CRC_16 for 16-bit

Definition at line **1504** of file **RF24.cpp**.

void RF24::disableCRC (void)

Disable CRC validation

Warning

CRC cannot be disabled if auto-ack/ESB is enabled.

Definition at line **1524** of file **RF24.cpp**.

```
void RF24::maskIRQ ( bool tx_ok,  
                    bool tx_fail,  
                    bool rx_ready  
                    )
```

The radio will generate interrupt signals when a transmission is complete, a transmission fails, or a payload is received. This allows users to mask those interrupts to prevent them from generating a signal on the interrupt pin. Interrupts are enabled on the radio chip by default.

```
Mask all interrupts except the receive interrupt:  
radio.maskIRQ(1,1,0);
```

Parameters

- tx_ok** Mask transmission complete interrupts
- tx_fail** Mask transmit failure interrupts
- rx_ready** Mask payload received interrupts

Definition at line **1024** of file **RF24.cpp**.

```
void RF24::openReadingPipe ( uint8_t  number,
                             uint64_t address
                             )
```

Open a pipe for reading

Note

For compatibility with old code only, see new function

Warning

Pipes 1-5 should share the first 32 bits. Only the least significant byte should be unique, e.g.

```
openReadingPipe(1,0xF0F0F0F0AA);
openReadingPipe(2,0xF0F0F0F066);
```

Pipe 0 is also used by the writing pipe. So if you open pipe 0 for reading, and then **startListening()**, it will overwrite the writing pipe. Ergo, do an **openWritingPipe()** again before **write()**.

Parameters

number Which pipe# to open, 0-5.

address The 40-bit address of the pipe to open.

Definition at line **1152** of file **RF24.cpp**.

```
void RF24::openWritingPipe ( uint64_t address )
```

Open a pipe for writing

Note

For compatibility with old code only, see new function

Addresses are 40-bit hex values, e.g.:

```
openWritingPipe(0xF0F0F0F0F0);
```

Parameters

address The 40-bit address of the pipe to open.

Definition at line **1113** of file **RF24.cpp**.

bool RF24::failureDetected

Enable error detection by un-commenting `#define FAILURE_HANDLING` in [RF24_config.h](#). If a failure has been detected, it usually indicates a hardware issue. By default the library will cease operation when a failure is detected. This should allow advanced users to detect and resolve intermittent hardware issues.

In most cases, the radio must be re-enabled via `radio.begin()`; and the appropriate settings applied after a failure occurs, if wanting to re-enable the device immediately.

Usage: (Failure handling must be enabled per above)

```
if(radio.failureDetected){
    radio.begin();                // Attempt to re-configure the radio with defaults
    radio.failureDetected = 0;    // Reset the detection value
    radio.openWritingPipe(addresses[1]); // Re-configure pipe addresses
    radio.openReadingPipe(1,addresses[0]);
    report_failure();             // Blink leds, send a message, etc. to indicate failure
}
```

Definition at line [673](#) of file [RF24.h](#).

uint32_t RF24::txDelay

The driver will delay for this duration when [stopListening\(\)](#) is called

When responding to payloads, faster devices like ARM(RPi) are much faster than Arduino:

1. Arduino sends data to RPi, switches to RX mode
2. The RPi receives the data, switches to TX mode and sends before the Arduino radio is in RX mode
3. If AutoACK is disabled, this can be set as low as 0. If AA/ESB enabled, set to 100uS minimum on RPi

Warning

If set to 0, ensure 130uS delay after [stopListening\(\)](#) and before any sends

Definition at line [920](#) of file [RF24.h](#).

uint32_t RF24::csDelay =5

On all devices but Linux and ATTiny, a small delay is added to the CSN toggling function

This is intended to minimise the speed of SPI polling due to radio commands

If using interrupts or timed requests, this can be set to 0 Default:5

Definition at line [931](#) of file [RF24.h](#).

The documentation for this class was generated from the following files:

- [RF24.h](#)
- [RF24.cpp](#)

